# Exam :   E20-360
# Network Storage - NAS Implementation

# Demo Version

**To Access Full Version, Please go to**

**www.itexamworld.com**

## QUESTION 1

Name the cable type which is used to connect from a com port on the Service PC to the Com port on the front of an NS600 Control Station.

A. Null Modem
B. Straight-thru
C. RJ11
D. Crossover

Answer: A

## QUESTION 2

Name what houses the Disk Array Enclosure [DAE2], rack mounted enclosure.

A. Two [2] Lick Controller Cards, two [2] Power Supplies and up to fifteen [15] Disk Drives
B. Four [4] Fibre Disk, eleven [11] ATA Disk Drives, two [4] Link Controller Cards and two [2] Power Supplies
C. Up to fifteen [15] ATA Disk Drives, two [2] Link Controller Cards and two [2] Power Supplies
D. Four [4] Disk Drives, two [2] Power Supplies and two [2] Lick Controller Cards

Answer: A

## QUESTION 3

The following error message is displayed, upon issuing NSLOKUP:
*** can't find server name for address 192.168.10.5
Name the record which is missing from the DNS zone.

A. Name Server
B. PTR
C. Start of Authority
D. Forward Zone

Answer: B

## QUESTION 4

What is a characteristic of the password used, when joining a data mover to a Windows 2000 domain?

A. must contain both alpha and numeric characters
B. must have been changed at least once
C. must be at least 8 characters long
D. is not case sensitive

Answer: B

---

## QUESTION 5
Name the command which allows you to view open connections and open files for CFIS.

A. servercifsstat
B. servercifs
C. servernetstat
D. serversysstat

Answer: A

---

## QUESTION 6
You are required to match the architecture of the NS600 and NS600G with its description, as a Itexamworld .com instructor.

| | Description |
|---|---|
| Place here | NS600 |
| Place here | NS600G |

| | |
|---|---|
| Shared Back End with Dual Data Mover | Dedicated Back End |
| Single Data Mover Dedicated Back End | Single Data Mover Fibre or Direct Connect |

Answer:

| | Description |
|---|---|
| Dedicated Back End | NS600 |
| Shared Back End with Dual Data Mover | NS600G |

| | |
|---|---|
| Single Data Mover Dedicated Back End | Single Data Mover Fibre or Direct Connect |

---

## QUESTION 7
All disk drives have a private area not accessible to the user. What is the private area used for, on the first DAE2, on disk 0-4,?

A. Access files faster
B. Error Log
C. Vaulted Area
D. Fast Cache

Answer: C

---

**QUESTION** 8
You have connected your Service laptop to the control station com port using Hyper
Terminal and the proper cable, after booting the control station with the boot floppy.
Now you are at the boot prompt.
Name which option you would choose to complete a new install of an NSx00G.

A. Serialupgrade
B. INSTALL
C. SERIALINSTALL
D. setup

Answer: C

---

**QUESTION** 9
Name the NS600G/GS component which is used to attach to an existing CX600.

A. Internal Ethernet switch
B. Serial Connection Assembly
C. Direct or SAN attached to SP-A and SP-B
D. Direct attach to SPS-A and SPS-B

Answer: C

---

**QUESTION** 10
Name which TCP feature allows the receiver to inform the sender of exactly which data
has been received, allowing the sender to retransmit only missing data and not data that
has been successfully received.

A. Partial packet retransmission
B. RACK (Relative Acknowlegment)
C. TCP Reconnect
D. SACK (Selective Acknowledgement)

Answer: D